

Helpdesk XIMEA

Portal > Knowledgebase > xiAPI & Software Package > xiApiPython > XIMEA Python API - macOS installation steps

XIMEA Python API - macOS installation steps

Support SK - 2023-10-19 - in xiApiPython

https://www.ximea.com/support/wiki/apis/python_inst_macos

XIMEA Python API - macOS installation steps¹



How to install the Ximea Python module:¹

1. **Install the Ximea SP** - Follow the instructions from [this](#) site and run the install script.
2. **Check the installation** by calling this command:

```
python -c "import ximea;  
print(ximea.__version__)"
```

It should print out the version of the package.